TRANOS WEB TECHNOLOGIES

TrendIndicator EA for MT4

Comprehensive User Manual

Manual-first MT4 workflow
A practical, illustrated guide to the visible chart controls, trade management and order workflows.

Current-release additions covered: automatic move stop loss to entry, trigger in pips or account currency, and configurable partial close at break-even.

Read this guide before using the EA. Test each workflow on a demo account. TrendIndicator provides contextual tools—not investment advice, profit guarantees or an unattended income system.

Version: Current illustrated release

Contents

1. Purpose, limits and responsible use

2. Before you trade

3. Reading the multi-timeframe strength

4. S/R Verdict and optional one-shot Auto Trade

5. Placing a manual BUY or SELL

6. Automatic Move SL to Entry + partial close

7. Manual Pending Orders

8. Chart zones, news and dashboard

9. Practical operating checklist

10. Troubleshooting and support

How to use this manual

The screenshots are real MT4 TrendIndicator interface captures annotated for orientation. Screen layout, colours and the exact chart symbol may vary with your broker, display scale and version. The Auto BE figure is an illustrated current-release control layout because the supplied archive screenshots predate that control row.

Interface map

Start here: the five areas below make up the normal chart workspace. The number tags in the screenshot correspond to the descriptions immediately below it.




Annotated real MT4 chart capture. It is an orientation map—not a trade recommendation.

Area	What it is for
1. Main panel	**Trend context, Manual Lot, Manual SL/TP, BUY, SELL and trade-management controls.**
2. S/R Verdict	**Visible support/resistance context, intended side and the separately armed one-shot Auto Trade control.**
3. Pending Orders	**Manual Entry/SL/TP preparation and explicit pending order buttons.**
4. Chart zone drawings	**Contextual support/resistance presentation for trader review.**
5. Dashboard	**At-a-glance multi-symbol context; always confirm the active chart before acting.**

Multi-timeframe strength and overall verdict


Arrow 1 marks Direction Strength: a signed directional evidence display, not a probability. Arrow 2 marks the five separate M30/H1/H4/D1/W1 readings. Arrow 3 marks the overall verdict. MODERATE UP (3/5) means exactly three of five monitored timeframes are aligned upward and ready; it is tradable context, not a guarantee.



Numbered arrows: 1 Direction Strength · 2 Multi-TF rows · 3 overall verdict.

S/R Verdict and optional one-shot Auto Trade


Arrow 1 marks the S/R Verdict headline and supporting context. Arrow 2 marks the Intended Trade text: it provides direction context but does not place an order. Arrow 3 marks AUTO TRADE. This separate control starts OFF, ignores a verdict already present at arming, and can attempt one order only after a new strong verdict. It then disarms. Verify Manual Lot and displayed SL/TP first.



Numbered arrows: 1 verdict · 2 intended trade context · 3 deliberate one-shot Auto Trade arm/disarm.

Manual market trade controls


Arrow 1 marks Manual Lot. Arrow 2 marks Manual SL, Manual TP and the PIPS/account-currency unit button. Arrow 3 marks BUY/SELL for manual market execution. Arrow 4 marks Take Profit / Close All. Arrow 5 marks the immediate manual MOVE SL TO ENTRY protection action. Review the market and your risk before pressing any order control.



Numbered arrows: 1 Manual Lot · 2 SL/TP and unit · 3 BUY/SELL · 4 Close All · 5 Move SL to Entry.

Manual Pending Orders


Arrow 1 marks the planned Entry/SL/TP fields. Arrow 2 marks Use Current Price, a convenience fill only. Arrow 3 marks the four explicit pending-order types; you must choose the correct one. Arrow 4 marks the timeframe recommendation area. It may fill values for review, but Reload cannot submit an order without your deliberate pending-order button click.



Numbered arrows: 1 Entry/SL/TP · 2 current-price fill · 3 order types · 4 recommendation/reload.

Current Auto BE and partial-close controls

This release adds a visible automatic break-even layer. It is independent of the Auto Trade feature. Use the on-panel switch, trigger and unit selection, and Close at BE percentage to configure it for the current attachment session.



Illustrated current-release control layout. Example values only.

1. Purpose, limits and responsible use

TrendIndicator EA for MT4 is a chart-side analysis and trading-workflow tool. It presents trend context, multi-timeframe alignment, support/resistance context, manual market and pending-order controls, optional alerts, news context, a dashboard and trade-management controls in one chart workspace.

It is not investment advice, a managed account, a profit guarantee, or an unattended income system. Market conditions, spread, slippage, broker restrictions, connection quality and user settings affect every result. Test all workflows on a demo account first and make your own decision before every live order.

This manual explains visible user controls only. It deliberately does not disclose proprietary formulas, weighted scoring, internal thresholds, source code, or entry-logic construction.

2. Before you trade

Install only the compiled EA supplied with your license. Attach it to the intended chart, confirm the chart symbol and account currency, and ensure MT4's trading permissions are configured appropriately for your broker.

Before pressing a trading control, confirm: the correct symbol and timeframe; Manual Lot; SL/TP mode; spread and broker stop distance; whether an existing order belongs to this EA; and whether you are using a demo account while learning the workflow.

Auto Trade and Auto BE are separate features. Auto Trade is always OFF after attach/restart. Auto BE starts ON by default in the current release, but the trader can turn it off on the panel.

8. Chart zones, news and dashboard

Support/resistance drawings and labels are visual context. They do not execute orders and do not guarantee that a level will hold or break. Review current price action, spread and your own risk plan.

The optional news panel reports upcoming calendar context when its network/WebRequest configuration is available. If it is unavailable, verify the documented MT4 WebRequest setting and connectivity. News information is contextual; it is not a trading recommendation.

The dashboard provides compact multi-symbol visibility. A dashboard row helps you compare context, but it is not a portfolio instruction. Always confirm the exact symbol, lot, direction and risk settings on the active chart before acting.

9. Practical operating checklist

Before a manual trade: check symbol, direction, Manual Lot, SL/TP unit and values, spread, broker limitations and your maximum risk.
Before Auto Trade: additionally check the displayed intended side, then arm only for a new event and expect at most one attempted order.
Before Auto BE: check the ON/OFF state, trigger unit/value and Close at BE percentage.
Before a pending order: check Entry/SL/TP price relationships and choose the exact order type.
After every action: check the MT4 Trade tab and Experts/Journal output.

10. Troubleshooting and support

If a panel control is missing, confirm that you installed the latest compiled EA, recompile the current source in MetaEditor if you are working from the source file, refresh/re-attach it and check chart size/display scaling.

If an order is rejected, record the MT4/broker error, symbol, current price, spread, intended order type, lot size and stop-distance context. Do not share account passwords, payment details, license secrets or credentials.

For support, send a chart screenshot and relevant MT4 Experts/Journal lines through your support channel. Technical contact: tranoswebtech@gmail.com.

Control-by-control reference

Control	Use	Important limit
Manual Lot	**Sets the lot size for manual market and pending orders.**	**Must comply with broker minimum/maximum and lot step.**
Manual SL / TP	**Sets stop loss and take profit in PIPS or account currency.**	**0 leaves the respective stop unset; broker distance rules apply.**
BUY / SELL	**Submits a manual market order.**	**Review every order; it is not a signal confirmation button.**
MOVE SL TO ENTRY	**Moves eligible EA trade protection to the entry price.**	**Does not manage unrelated/manual trades; broker rules apply.**
AUTO MOVE SL	**Enables/disables automatic break-even management.**	**Applies only to eligible EA market orders on the chart symbol.**
Trigger + unit	**Sets the Auto BE profit trigger in PIPS or account currency.**	**Currency trigger uses net floating P/L; choose a realistic value.**
Close at BE	**Sets the partial close percentage when Auto BE triggers.**	**1–99% only. Unsupported broker-lot combinations are skipped, never full-closed.**
AUTO TRADE	**Arms exactly one possible order for a future new strong verdict.**	**Starts OFF; it is not continuous unattended trading.**
Pending order buttons	**Places the selected pending type using entered values.**	**You choose the type and remain responsible for entry/SL/TP validity.**

8. Chart zones, news and dashboard

Support/resistance drawings and labels are visual context. They do not execute orders and do not guarantee that a level will hold or break. Review current price action, spread and your own risk plan.

The optional news panel reports upcoming calendar context when its network/WebRequest configuration is available. If it is unavailable, verify the documented MT4 WebRequest setting and connectivity. News information is contextual; it is not a trading recommendation.

The dashboard provides compact multi-symbol visibility. A dashboard row helps you compare context, but it is not a portfolio instruction. Always confirm the exact symbol, lot, direction and risk settings on the active chart before acting.

9. Practical operating checklist

Before a manual trade: check symbol, direction, Manual Lot, SL/TP unit and values, spread, broker limitations and your maximum risk.
Before Auto Trade: additionally check the displayed intended side, then arm only for a new event and expect at most one attempted order.
Before Auto BE: check the ON/OFF state, trigger unit/value and Close at BE percentage.
Before a pending order: check Entry/SL/TP price relationships and choose the exact order type.
After every action: check the MT4 Trade tab and Experts/Journal output.

10. Troubleshooting and support

If a panel control is missing, confirm that you installed the latest compiled EA, recompile the current source in MetaEditor if you are working from the source file, refresh/re-attach it and check chart size/display scaling.

If an order is rejected, record the MT4/broker error, symbol, current price, spread, intended order type, lot size and stop-distance context. Do not share account passwords, payment details, license secrets or credentials.

For support, send a chart screenshot and relevant MT4 Experts/Journal lines through your support channel. Technical contact: tranoswebtech@gmail.com.